# MIC Intro Lab

**IXPUG 2014** 



#### Part 0 – Grab the Lab Files

- Login to Stampede
  - \$ ssh <username>@stampede.tacc.utexas.edu
- Untar the file lab1.tar file (in ~train00) into your directory:
  - \$ tar xvf ~train00/lab1.tar
- Move into the newly created lab1 directory:

```
$ cd lab1 # first char is lower case "L"; last is a one
```

- \$ pwd
- \$ 1s



# Part 1 – Run an MPI Batch Job (sbatch)

Compile the mpipi program:

```
$ mpicc mpipi.c -o mpipi
```

Open the batch script in an editor to see if you need to hange it:

Launch the batch job

```
$ sbatch lab1batch
```

Monitor the job's status (when done, ommand will return nothing):

When job complete, take a look at results:

```
# Note presence/names of output files
prove mpipi.xxxxx.out # "xxxxx" is your job's jobid
more mpipi.xxxxx.err # "xxxxx" is your job's jobid
```



### Part 2 – An Interactive Session (idev)

Launch a one-node interactive session using a special reservation

```
$ idev
```

When session begins, compile hello.F90\* from compute node:

```
$ ifort -openmp hello.F90 -o hello
```

Run the code:

```
$ ./hello # you're on a compute node, not a login node
```

Set OpenMP threads and try again

```
$ export OMP_NUM_THREADS=4
$ ./hello
```

\*Note: the capital "F" in the suffix instructs the compiler to interpret the macros in the source code. If the suffix were "f90" the compilation would require a "-cpp" flag.



# Part 3 – Run MIC App from the Host

• While on the compute node, recompile to produce "native MIC" code (compilers are not visible from the MIC):

```
$ ifort -mmic -openmp hello.F90 -o helloMIC
```

Launch the MIC code from the host:

```
$ ./helloMIC
```

Note: the program reports 244 "processors" because each MIC core has four hardware threads. It may not be efficient to run this many threads.

From the host, modify the MIC thread count and try again:

```
$ export MIC_OMP_NUM_THREADS=60
$ export MIC_ENV_PREFIX=MIC
$ ./helloMIC
```



### Part 4 – Visit the MIC

• Go the MIC using ssh:

```
$ ssh mic0  # the "zero" identifies the MIC card
```

Move into the lab1 directory with explicit cd (alias and env variable not avail):

```
$ cd lab1
```

Run your MIC code:

```
$ ./helloMIC
```

• Change the MIC's thread count and run code again (don't use "MIC" prefix):

```
$ export OMP_NUM_THREADS=25
$ ./helloMIC
```

Return to host, then end srun session as desired:

```
$ exit  # to return to host
$ exit  # to end idev session
```

